

How to use the “YoLink™ Device Service” app a Hubitat™ Hub

(Version 1.1)

The YoLink™ Device Service app (hereafter referred to as simply, “the Service”) consists of the YoLink™ Device Service app and various device drivers that support the different YoLink™ devices.

This document assumes that you have already installed the Service and associated drivers on your Hubitat™ hub as detailed in the document:

[How to install the YoLink™ Service App](#)


(https://github.com/srbarcus/yolink/blob/main/Help/How_to_install_the_YoLink_Service_App.pdf)

The list of currently supported devices, and those currently under development, can be found at:


[Supported Drivers](#)

(<https://raw.githubusercontent.com/srbarcus/YoLink/master/Drivers.txt>)


1. Open the Hubitat mobile app and click on “Connect to hub”:



2. Click on “Apps”:







3. Click on the “YoLink™ Device Service”:






4. Click "Next":

Optional: Click on "Make a Paypal donation..." to make a donation to the developer. Thank you in advance.

5:01

http://192.168.1.240/installedapp/configure/279

YoLink™ Device Service

ABOUT


YoLink™ Device Service - Version 2.1.10

This app connects your YoLink™ devices to Hubitat via the cloud.

The app is neither developed, endorsed, or associated with YoLink™ or YoSmart, Inc.
Provided 'AS IS', without warranties or conditions of any kind, either expressed or implied.

Refer to the [Hubitat Community Discussion](#) for the latest information and installation help.


Please donate and support the development of this application and future drivers. This effort has taken me hundreds of hours of research and development:


Make a Paypal donation...
Click to show

© 2022, 2023 Steven Barcus. All rights reserved.

WARNING: Removing this application will delete all Hubitat devices created by the app! (This option can be disabled in the additional settings before removal)

Enable Debugging *

False



RemoveNext

5. Enter your Personal Access Credentials from the YoLink™ mobile app. You can click on the “How to obtain your User Access Credentials” to view the instructions on how to locate them in the YoLink™ mobile app. Insure upper and lowercase letters, as well as similar looking characters such as '0' (zero) and 'O' (oh) and '1' (one) and 'l' (ell), are specified exactly as shown in the YoLink™ mobile app:

The screenshot shows a mobile web browser interface for 'YoLink™ Device Service'. The address bar shows the URL '192.168.1.240'. The page title is 'YoLink™ Access Credentials'. The main content area has a blue gear icon in the top right corner. The text reads: 'These values must match the YoLink™ mobile app values precisely. Take care to insure upper and lowercase letters, as well as similar looking characters such as '0' (zero) and 'O' (oh) and '1' (one) and 'l' (ell), are specified exactly as shown in the app.' Below this, it says 'User Access Credentials from the YoLink™ mobile app'. There are two input fields: 'UAID:*' with the placeholder 'ua_.....' and 'Secret Key:*' with the placeholder 'sec_v1_.....'. Below the input fields, there is a link: 'Click here for information on obtaining your User Access Credentials from the YoLink™ mobile app'. A button labeled 'How to obtaining your User Access Credentials (UAC)' with a right arrow and the text 'Click to show' is present. At the bottom right, there is a 'Next' button. The footer contains links for 'Documentation', 'Community', 'Videos', and 'FAQ', along with 'Terms of Service' and 'Copyright 2022 Hubitat, Inc.'.

YoLink™ Access Credentials

These values must match the YoLink™ mobile app values precisely. Take care to insure upper and lowercase letters, as well as similar looking characters such as '0' (zero) and 'O' (oh) and '1' (one) and 'l' (ell), are specified exactly as shown in the app.

User Access Credentials from the YoLink™ mobile app

UAID:*
ua_.....

Secret Key:*
sec_v1_.....


Click here for information on obtaining your User Access Credentials from the YoLink™ mobile app

How to obtaining your User Access Credentials (UAC)
Click to show

Next

Documentation Community Videos FAQ
Terms of Service Copyright 2022 Hubitat, Inc.

6. If the credentials you enter are invalid, you will receive the following error panel. Click “Next” to re-enter the credentials:



7. If the YoLink™ Device Service connects to your YoLink™ hub successfully, the “Other Settings” panel is displayed. Change the settings as desired and click “Next”:

5:02

http://192.168.1.240/installedapp/configure/279

1

YoLink™ Device Service

Other Settings

Temperature Scale (Celsius or Fahrenheit)

Scale used to report temperatures on newly defined devices. Can be overridden individually on each device definition. *

F

Device polling interval in minutes

Interval at which devices are polled. Mostly used to determine if device is still online, but some devices may need to be polled to update their settings. 5 Minutes is the recommended interval. *

5

Synchronize device names with YoLink Mobile app

Forces devices to be renamed to match their name in the YoLink Mobile application. To synchronize the names, simply rerun this app from start to finish after renaming the device(s) in the YoLink mobile app. *

True


Remove associated Hubitat devices when this app is removed

This is for advanced users only. Setting it to False will result in orphaned device definitions if the app is removed. *

True


Next

8. The following panel is displayed showing the number of YoLink™ devices that were found. Click on “Click to choose” to open a drop-down list of devices found:







9. Click on each of the devices that you want to install and control from your Hubitat™ hub. Make sure you scroll the list of devices and not just the page as the box might be longer than the page:





Note: Not all YoLink™ devices are currently supported. Check your Hubitat™ hub's log after installation is complete to see if there are any error messages indicating that an appropriate device driver was not found.




10. Click on the selection box again to close the list of devices and then click “Next” to install the devices. NOTE: No new panel will appear immediate after clicking “Next”. It may take several minutes to install all the devices on the Hubitat™ hub, especially if your list of devices is extensive. A green “spinner” will appear at the top of the panel indicating that the install is in progress. DO NOT INTERRUPT THE PROCESS! :

5:09


http://192.168.1.240/installedapp/configure/279

YoLink™ Device Service



36 devices found. Select the devices you want available to Hubitat


Click below to see the list of devices available in your YoLink home

Backyard Gate, Basement Refrigerator, Basement Temperature, Br... 

Note: Clicking 'Next' will create the selected devices and/or delete the deselected devices. This will take awhile if you have many devices, please be patient.

Next

11. When the installation of the selected devices is complete, the “Diagnostics” panel will appear. These should be set to “False” unless working with the Developer to diagnose a problem. Click “Done”:



The screenshot shows a web browser window with the address bar displaying `http://192.168.1.240/installedapp/configure/279`. The browser's address bar also shows a shield icon, a flame icon, a tab with the number '1', and a menu icon. The page title is 'YoLink™ Device Service'. The main content area is titled 'YoLink™ Device Service Diagnostics' and features a blue gear icon in the top right corner. A red warning message states: 'Only set these options to True if instructed to by the Developer. No personal information is collected or sent. The diagnostics data is written to a file on your Hubitat so you can see what's collected.' Below this, there are two configuration options, each with a dropdown menu currently set to 'False':

- 'Perform a reset on all YoLink™ devices *'
- 'Enable collection of diagnostic data to local file. *'

A 'Next' button is located at the bottom right of the configuration area.

5:10

http://192.168.1.240/installedapp/configure/279

YoLink™ Device Service

YoLink™ Device Service Diagnostics

Only set these options to True if instructed to by the Developer. No personal information is collected or sent. The diagnostics data is written to a file on your Hubitat so you can see what's collected.

Perform a reset on all YoLink™ devices *


False

Enable collection of diagnostic data to local file. *

False

Next

12. Open the “Devices” section on your Hubitat™ hub and you should see all the (supported) devices – they all start with the work “YoLink”:



13. Additional information:

1. You can use the “Modify” option of the “Hubitat Package Manager” app to install new device drivers if you acquire a new type of device or new drivers become available.
2. You can use the “YoLink™ Device Service” app to add or remove devices on your Hubitat™ hub, simply select or deselect the device(s) in the device list as shown in step 7 above. Note: If you uninstall a device and then reinstall it later, it will be a completely new device on the Hubitat™ hub.